



Install the software of data recorder

You can find four install programs as follow in compressed package.



Step 1 Unzip compressed package to your computer.

Step 2 Install the program of **AccessRun time**:



A. Double click this icon in software package.

B. Program auto installed as follow picture:




C. When the installation complete, close the dialog box.



Step 3 Run the program of Setup 1 :

A. Double click this icon

B. Click next as directed :



C. Choose your destination of folder, then click the next:





D. Click the next:



E. When the installation complete, close the dialog box.



F. You will find the quick icon in your desktop






Step 4 This software is compatible to Windows 7 system, If your computer is installed other system, please do this step to modify software compatibility



- A. Right click the icon in your desktop.
- B. Click the **Attribute**:




- C. Click the **compatibility**:





D. Select "run in compatibility mode". In the list, choose "Windows XP (Service Pack 3)", then click **confirm**.



Step 5 Run the software and login in, get **registration code**




- A. Double click the icon in your desktop.
- B. Select the suitable **language**, click the **Enter**.





C. Click the “Register”



D. Copy Your machine code (example is F3501C2B)





E. Double click this icon of  in **software package**. Paste your machine code in the upper window:




F. Click the **get button** to get the **registration code**:






G. Fill in the obtained registration code on the **registration page**, click the **Register**.



H. The registration **completed interface** as follow:



Now you can start to use the software.